

Onboarding - How to Setup Kiosk Mode

Last Modified on 09/17/2026 9:09 am CDT

Overview

Kiosk mode lets you leave a shared device, a tablet or lobby computer, open to an onboarding form. The screen automatically clears between employees so no one's information lingers for the next person.

Kiosk mode is a wrapper page that displays your onboarding form inside a full-screen frame. Two things keep it safe for shared use:

- **Auto-Reset on Inactivity.** If no one interacts with the screen for 3 minutes, a 30-second countdown appears. If still no activity, the page reloads and returns to the start of the onboarding form — ready for the next person.
- **Manual Reset Button.** A Reset button is always visible in the top-right corner. Staff can tap it at any time to immediately clear the screen.

How to Setup Kiosk Mode

1. Get Your Kiosk URL

- Your TempWorks Onboarding contact will provide you with a "Kiosk URL" specific to your account. For example, [https://app.onboarded.com/tempworks/kiosk?render_url=\[your-onboarding-link\]](https://app.onboarded.com/tempworks/kiosk?render_url=[your-onboarding-link])
- The "render_url" is your TempWorks Onboarding Link, typically a job-apply or branch-selection URL tied to your account. If you don't have it, reach out to your TempWorks Onboarding contact before continuing.

2. Open the Kiosk URL on Your Device

- Open a browser on the device you're using as the kiosk (tablet, desktop, or any device with a browser).
- Navigate to your "Kiosk URL". The page loads with your onboarding form in the center and a "Reset" button in the top-right corner.
- Put the browser in full-screen mode (usually "F11" on desktop or use your browser's full-screen option). This prevents employees from accidentally navigating away from the kiosk.
 - ***Note*** Keep the browser tab open. If the tab is closed and reopened, the session restarts, and any form data in progress is lost.

3. Employee Completes Onboarding at the Kiosk

- Direct the employee to the device. They complete the onboarding form normally.
- When they're done, they (or a staff member) can select "Reset" to immediately clear the screen for the

next person. The screen clears automatically after 3 minutes of inactivity.

Branch Selection

If your "Kiosk URL" includes branch selection, employees see a screen asking them to select a branch (searchable by postal code) before the onboarding form loads. Once a branch is chosen and "Continue" is selected, the form opens with that branch pre-set.

Troubleshooting

- **The screen isn't auto-resetting** The auto-reset only works when the onboarding form is served from the same domain as the kiosk page (app.onboarded.com). If your "render_url" points to a different domain, the inactivity timer is paused. Select the manual "Reset" button and contact your TempWorks Onboarding contact to get the correct URL.
- **The countdown appeared but the employee is still using the form.** Any interaction (tap, scroll, or keystroke) resets the inactivity timer. If an employee is actively using the form, the countdown disappears as soon as they interact with it.
- **The form isn't loading.** Check that the device has an internet connection and that the "render_url" in your "Kiosk URL" is correct. You can paste the "render_url" value into a new browser tab to verify it loads on its own.

Related Articles