


TimeIntel by TempWorks Configuration Options

Last Modified on 07/07/2026 1:05 pm CDT

What is TimeIntel by TempWorks?

TimeIntel by TempWorks, or TI, allows you to use just about any tablet or phone device as a time clock for your employees to punch in and out from. This process uses the TI application for punching and our WebCenter platform for reviewing and approving time.



The screenshot shows the TimeIntel by TempWorks login interface. At the top, there is a logo consisting of a clock face with a stylized 'i' inside, followed by the text 'TimeIntel' in a large, bold, blue font, and 'By TempWorks' in a smaller, regular blue font below it. In the top right corner, there is a hamburger menu icon. Below the logo, the date 'Tue, Jul 07, 2026' is displayed, followed by the time '10:53 AM' in a large, bold, black font. Underneath the time, the text 'Enter your 6-digit PIN' is shown. Below this text are six input boxes, each containing a single asterisk. To the right of the input boxes is a small icon of a crossed-out eye. Below the input boxes is a large, dark blue button with the text 'Sign in' in white. At the bottom of the screen, there is a QR code icon followed by the text 'Sign in with QR code'. Below this, there is a circular icon with an 'i' inside, followed by the text 'PIN Info'. At the very bottom, there are two buttons: one with the US flag and the text 'ENG', and another with the Mexican flag and the text 'ESP'.

 **TimeIntel**
By TempWorks

Tue, Jul 07, 2026
10:53 AM

Enter your 6-digit PIN



Sign in

 [Sign in with QR code](#)

 PIN Info

 ENG  ESP

Note The TimeIntel by TempWorks application requires Beyond access to function. Please contact your TempWorks Account Manager for more information.

The TimeIntel by TempWorks application is a licensed product. If you would like to utilize this application, please reach out to your TempWorks Account Manager.


This article reviews specific WebCenter configurations you can set up with the TimeIntel by TempWorks application.

To Locate Configuration Options in WebCenter:

1. Navigate to WebCenter Admin
2. Select the Config tab:



3. Choose TimeClock Category:



Enabling On-Site Time Punches

Enable On-Site Time Clock App Punching configuration is required in order for the TimeIntel by TempWorks application to allow and send time clock punches to WebCenter.

Enable On-Site Time Clock App Punching Default: false [Hide Rules \(1\) ▼](#)

Used by the On-Site Time Clock App. If turned on employees will be able to punch into the On-Site Time Clock App.

Rules

When: Select a filter.. ▼ is ▼ Use: ☐ True ☐ False Add Rule

[Edit](#) When Customer is 100 Acre Woods, Inc. (4295000614) HiTechQA-2 ✖

Use True

Note For more information, please see the article titled [How to Setup TimeIntel by TempWorks](#).

Enabling Facial Recognition

You can utilize facial recognition to require a facial verification every time any employee punches in or out. This is in addition to their log in method.

To turn this feature on, first create a new rule for the **Enable On-Site Time Clock Face Verification** configuration:

Enable On-Site Time Clock Face Verification Default: false [Hide Rules \(0\) ▼](#)

Used by the On-Site Time Clock App. If turned on employees will be required to take a picture of themselves with their phone when they punch and the punch will not succeed unless the picture is verified to be the employee.

Rules

When: Customer ▼ is 100 Acre Woods, Inc. (4295000614) ▼ Use: ☒ True ☐ False

[Add Rule](#)


If you are having trouble with employee's facial recognition acceptance, you can create rules on the **On-Site Time Clock Face Verification Confidence Threshold** config to change the threshold. (We recommend keeping it at the 80%)

On-Site Time Clock Face Verification Confidence Threshold Default: 80 [Show Rules \(0\) ►](#)

Used by the On-Site Time Clock App. How confident the face verification system must be that the image taken is the employee before allowing a punch to succeed. Entered value is a percent value from 0 to 100. Default is 80 for 80%.

Once you have turned on the facial recognition configuration, you will need to make sure your employees are set up with a facial recognition profile. We recommend doing this during an orientation or before they start as it can take a few minutes.

Navigate to their Web User Account Details (Via the  charm) and select the "Create Facial Verification Profile" action in the  menu beside the Buzz app web user product.



The employee will be prompted to set up their facial verification profile when clocking in the first time on within the TimeIntel by TempWorks application.

Enabling Geofencing

If you are not mounting your device to a wall, you may want to use geofencing to ensure when employees are clocking in they are within the worksite. In WebCenter admin, create a rule under the **Enable On-Site Time Clock Geofencing** configuration to turn this option on per customer or department.

Enable On-Site Time Clock Geofencing Default: false [Hide Rules \(0\) ▼](#)

Used by the On-Site Time Clock App. If turned on employees will only be able to punch on assignments through the On-Site Time Clock App if they are within the boundaries of a punch location specified on their assignment's worksite.

Rules

When: Customer ▼ is 100 Acre Woods, Inc. (4295000614) ▼ Use: ☒ True ☐ False

[Add Rule](#)

Once you have turned this feature on, you will want to make sure your worksites are set up with punch locations:

1. Navigate to Customer > Details > Worksite and select the worksite:

CUSTOMER 100 Acre Woods, Inc. - Primary (4295000614) / Details / Worksites / Gloomy Place Warehouse

100 Acre Woods, Inc. (4295000614)
 Primary · 📍 Eagan, MN 55121

VISIFILE DETAILS ▾ DEFAULTS ▾ DOCUMENTS INVOICE HISTORY MESSAGES MORE

^ Worksite Details

Worksite Name	Gloomy Place Warehouse	Is Active	Yes
Address	123 100 AKER Drive Excelsior, MN 55331 United States of America	County	Hennepin
School District	--	Directions	Rather Sad and Boggy Place
Dress Code	Tails Optional	Time Zone	Central Standard Time
Observes Daylight Savings	Yes	Accessible to Public Transportation	No

Add

^ Punch Locations

No punch locations

- Select the "+" on the "Punch Locations" card
- Name the punch location and update your radius as necessary

Add Punch Location

Feel free to move the highlighted pin where you'd like it:

Name

Warehouse Assembly Line

Description

Determine an acceptable punch-in radius for your employees:

Radius

101.351


Feet

SAVE AS DRAFT

CANCEL

SUBMIT

- Select "Submit"



Note If you have not used geofencing before, there may be additional setup required in your system. Talk with your account manager or support team for more information.

Learn more about other configuration options:

- Check out our Standard TimeClock configurations by [clicking here](#).
- Check out our TimeClock Rule Configuration options by [clicking here](#).

Related Articles